

MASTER MENU USER MANUAL



bitonlive

V. 1.17.830.1

The information contained in this document is subject to change at any time without prior notification. If you want to learn more info about our product, please visit our web www.bitonlive.com.

Master menu


Master Menu is the tool that enables you to organize all applications **BitOnLive**, manage the automatic startup, set alternate paths for shared folders and the backup database.

Summary

Overview	2
Setting	2
Setting - Program List	3
Setting - Storage Drive.....	4
Setting - Database Server List.....	5

Overview

In the main screen shows the programs icons added by the user



By clicking on the **setting** button  opens the window of the **Master Menu** setup.

Setting


Through the list of options on the left, you can choose between:

- **Program List:** application management
- **Storage Drive:** to set the paths of the shared folder backup
- **Data Base Server List:** to set the paths of the backup database

Function keys:

	Save the configuration profile created
	Load the configuration profiles previously saved
	Save your changes to the Master Menu settings
	Closes the settings window without saving


Setting - Program List



In the main part of the window lists all the program insert.

Through the **Add** and **Delete** Buttons   it is possible to add a new application or delete the one selected in the list.

In the window that appears after you click add, it is possible to indicate the information relating to the application to manage by **Master Menu**.



Description: application name to display in **Master Menu**

User Name: username of the user that will display the application (if blank the application will be available to all users)

Filename: Name of the .exe file of the application to add (using the button opens the window to search for Windows)

Directory: path to the folder of the application file (will be set automatically once made the research through Filename)

Parameter 1/2/3: Additional parametric for application startup


Msec Delay Autostart: Time in millisecond delay automatic start

Autostart: Enables or disables the automatic application startup


Once setup click on OK  to confirm the changes or Abort  to cancel.

Setting - Storage Drive

In the main part of the window is visible the list of virtualized disks and several folders (main or backup) that refer to the virtualized disc.




Through the **Add** and **Delete** Buttons   it is possible to add a new virtual disk and assign the main path and up to 4 paths of backup or delete virtualization selected in the list.



Local Drive: Letter of the virtualized disk

Source 1: Through the **browse** button, select the root folder that should be virtualized and used as main source.

Source 2/3/4/5: through the **browse** button, select the folders alternatives that will be virtualized in the absence of connection with the source 1

Once setup click on OK  to confirm the changes or Abort  to cancel.

Connection Errors

In the event of error in connection with the main source will be displayed in the foreground an alarm message.




It is possible to disable the message by clicking on the  Snooze Alarm button

Once you have settled in any connection problems and restored functionality of the network it is possible to select the main source by clicking with the mouse on the reset button 

Setting - Database Server List

Through this function, you can set the addresses of the database backup in case of problems in connection with the principal database.



Check DataBase Connection: Enables or disables the connection test with the database

The Main DataBase: Address of the principal database

Check Interval (millisecond): time interval with which will be made the check of connection

Alternatives 1/2/3/4: addresses of the backup database